

Changing Shutter Stream Working Location

WINDOWS

Due to space limitations on my C: drive, I would like to change the location of the temporary files.

Step-by-step guide

For the Windows version of Shutter Stream here is what you need to do:

1. Move the **C:\Users\yourname\AppData\Roaming\IconaSys\ShutterStream** to your new location, say f:\ShutterStream
2. Start a command prompt as an administrator (type cmd.exe, then right click and select Run As Administrator)
3. From the command prompt, create a [junction point](#) as follows (change f:\yournewfolder with your new location):

```
mklink /J "C:\Users\yourname\AppData\Local\IconaSys\ShutterStream" "f:\ShutterStream"
```

4. Confirm the new location with the "dir" command:

```
C:\Users\yourname\AppData\Local\IconaSys>dir

Directory of C:\Users\yourname\AppData\Local\IconaSys\

11/25/2018  10:10 PM    <DIR>          .
11/25/2018  10:10 PM    <DIR>          ..
11/25/2018  10:10 PM    <JUNCTION>     ShutterStream [f:\ShutterStream]
              0 File(s)      0 bytes
              3 Dir(s)  97,594,851,328 bytes free
```



If you are still on XP and not Vista or Windows 7, you don't have mklink, but you can use the [junction](#) utility in the same way.

Related articles

- [Installing the Arduino Turntable Driver](#)
- [Changing Shutter Stream Working Location](#)
- [Live View Not Working Displays A Black Screen](#)
- [Shutter Stream Working Folder And Thumbnails Location](#)
- [Shutter Stream Software: Feature Videos](#)